

---

---

**FUGUE.6 RELEASE NOTES**

---

---

This section describes the Fugue.6 release of Interlisp-D. This version substantially improves the performance and reliability of key system components and fixes many bugs reported in earlier releases of Fugue.

We invite you to send comments, suggestions and bug reports to 1100Support@XEROX or to Xerox Special Information Systems, MS 2-143, 250 N. Halstead Street, Pasadena, CA 91107.

The following are the most salient aspects of the Fugue.6 Release.

- <1> Improved floppy disk system for the 1108.
- <2> Improved RS232 support including low-cost graphics printer support.
- <3> Various new window/display facilities:
  - Menu
  - New GETREGION and GETBOXREGION
  - New DOWINDOWCOM
  - Window with CARET does not need to be on top
  - Minimum sizes for windows
  - CREATEREGION
  - CHANGEBACKGROUNDBORDER
  - VIDEOCOLOR
- <4> New 1108 and 1132 microcode.
- <5> New case-insensitive string manipulation facilities.
- <6> New stream-dependent property handling end-of-line conventions.
- <7> System level support for load-time constants.
- <8> New/Improved LispLibrary and LispUsers packages.
- <9> Memory management handles large reference counts.
- <10> Sysouts may be installed directly from the 1108's rigid disk.
- <11> Miscellaneous
  - STORAGE function takes two optional arguments
  - EDITPREFIXCHAR now defaults to NIL
  - GENSYM generalized
  - ATOMHASH # PROBES (new function)

- Missing characters restored for NS printers
- Gacha replaced by Terminal for Interpress
- The precision of transcendental functions has been improved

### <1> 1108 Floppy Disk System.

One can use Interlisp-D on the 1108 to read, write, and otherwise interact with files on formatted floppy disks through standard Interlisp input/output functions.

Reliability has been substantially improved. The {FLOPPY} device is now monitor-locked, so multiple processes can successfully access the disk simultaneously. There is better protection against Control-B and Control-D. And it is no longer possible for Lisp to die with 0510 or 0580-0584 maintenance panel errors.

SYSOUT to {FLOPPY}. SYSOUTs may be created on floppies through Interlisp's SYSOUT and FLOPPY.MODE function, then later installed on the same or other Xerox 1108s through the "Installation Utility." It generally takes 3 to 5 floppies to store a sysout.

Further documentation is available in the *Xerox 1108 Users Guide*.

### <2> RS232 Support

Reflecting improvements in low-level IO processor code for the 1108, Interlisp-D RS232 performance is considerably improved: it will "Chat" and "Ftp" at 1200 baud now, and there are no more "Transmitter Wedged" errors.

FXPRINTER is a Lisp Library package which drives an Epson FX-80 printer using a serial (RS232) interface. See the discussion under new LispUsers packages.

Some new functions available since the Fugue.4 release. See the RS232 writeup for details.

RS232MODEMCONTROL - one arg, to set the modem control lines

RS232MODIFYMODEMCONTROL - hanges only the specified modem control lines

RS232MODEMSTATUSP - reads the modem status lines

RS232READSTRING - essentially a block input function; especially useful for time-critical applications

RS232BACKGROUND - cause the keyboard scanning interrupt to poll the RS232 UART; may permit asynchronous operation at up to 600 baud.

RS232CHAT will pay attention to the DSPSCROLL setting of the chat window, and will attempt to do "roll mode" rather than "wrap around" mode when the screen is full. Also, new menu selections in the RS232 chat window permit one to specify whether the remote host sends CR or LF for "newline", and whether typing the RETURN key should send a CR/LF or just CR.

The {RS232} device is created by RS232INIT, and one can obtain a stream interface to the RS232 port by (OPENSTREAM '{RS232}' INPUT).

### <3> Window/Display Changes.

- Menu changes: submenus, item boxing, menu title fonts, and popup menus that don't tie up the mouse.

Items in a menu can now have subitems associated with them. An item with a submenu is marked in the menu by a grey, right pointing triangle. If the user drags the cursor out the right side of such an item, the submenu pops up. If the user selects one of the items from the submenu, the selected item is handled as if it were selected from the main menu. If the user rolls out of the submenu to the left, the submenu is taken down and selection resumes from the main menu.

Menus now have a new field SUBITEMFN which determines if a menu item has subitems. The SUBITEMFN is called with two arguments -- a menu and an item in that menu -- and should return a list of items (from which a submenu would be constructed) or NIL. The SUBITEMFN is called once to compute the menu image and again each time the user rolls out of the item box, so the SUBITEMFN should be moderately efficient. The default SUBITEMFN (named DEFAULTSUBITEMFN) checks to see if the item is a list whose fourth element is a list whose CAR is 'SUBITEMS and if so, returns the CDR of it. The standard interpretation of items that are LISTP is that the first element is the label, the second the form to be evaluated and returned and the third the help string. The rest of the list has been advertised as available for other uses, and we hope that no other use developed so far involves a list whose car is 'SUBITEMS.

Submenus are computed the first time they are needed and cached in the menu. This means that changes to subitems will not be noticed unless the item did not already have a submenu.

Other changes to the menu package:

The menu package now marks the item the cursor is over with a box when the button is not down. This is the way Dedit's menu works now.

MENU contains a new field MENUTITLEFONT which indicates the font to be used for the title of the menu. It should be either a font, NIL or T. NIL will cause the window title font to be used (the standard now). T means use the same font as the menu items.

MENU now takes an argument, RELEASECONTROLFLG, which allows the mouse to be used for other things while the popup menu is in place. For example, the user may need to look around for information needed to determine the selection to make in this menu or reposition the menu before selecting from it. If MENU is called in this way, clicking outside the menu (which is the standard way of indicating "no choice" to normal popup menus) will not return NIL. This effect can be had by closing the menu (which causes NIL to be returned from MENU). Programmers are encouraged to provide a menu item such as "cancel" or "abort" which gives users a positive way of indicating "no choice".

- Changes to GETREGION and GETBOXREGION. When passed a minimal region (as in shaping a window), they prompt with the minimal region. They also prompt from the lower right corner and won't let the user specify a region that is off the screen.
- DOWINDOWCOM now checks for the window property DOWINDOWCOMFN and if non-NIL applies it to the window.
- The window containing the CARET no longer jumps on top in order to flash the CARET. When the CARET is completely obscured it does not flash at all.
- The system supports the notion of a minimum size for a window. The new function MINIMUMWINDOWSIZE returns a dotted pair whose CAR is the minimum width and whose CDR is the minimum height. The window property MINSIZE allows the user to set the minimum size of a window and should be a dotted pair or a function which when APPLIED to the window returns a dotted pair. SHAPEW will not shape a window smaller than its minimum.
- (CREATEREGION Left Bottom Width Height) is defined to return the same thing as (CREATE REGION LEFT ← Left BOTTOM ← Bottom WIDTH ← Width HEIGHT ← Height).

- (CHANGEBACKGROUND BORDER Shade), where shade is a texture 8 bits wide by 2 bits high, sets the 1108 display border. CHANGEBACKGROUND BORDER is a no-op on the 1100 and 1132.
- VIDEOCOLOR now works on the 1108.

#### <4> New microcode.

- New 1108 Lisp microcode. Some operations previously in 1108 Lisp microcode have been moved into the initial microcode, and replaced by other opcodes.
- New 1108 initial microcode. The process of installing Fugue.6 with the Installation Utility floppy will load new initial microcode into your 1108. Note that while the new initial microcode is compatible with all Fugue sysouts, the Fugue.6 version of Interlisp-D will only run with the new initial microcode. In addition, the new initial microcode depends on up-to-date PROMs: if Fugue.4 worked on your 1108, but the new initial microcode and new sysouts do not, contact 1100Support.
- New 1132 microcode. A number of improvements, especially for "creation" of datatypes and for numerical operations.

#### <5> Case-insensitive string manipulation facilities.

UPPERCASEARRAY [Variable]

A casearray suitable for FFILEPOS et al, in which every lowercase character is mapped into the corresponding uppercase character. Useful for searching text files.

Extension to ALPHORDER:

(ALPHORDER A B CASEARRAY) [Function]

ALPHORDER now takes a casearray argument: characters of A and B are translated through CASEARRAY before being compared. In addition, the value returned in the "true" case, i.e., when A and B are in lexicographic order, is now either EQUAL or LESSP to discriminate the cases of A and B being equal or unequal strings/atoms (according to CASEARRAY).

New function:

(UALPHORDER A B)

[Function]

Defined as (ALPHORDER A B UPPERCASEARRAY). Suitable as the comparefn argument of SORT.

#### <6> Stream-dependent property for handling end-of-line conventions

Fugue.6 supports end-of-line convention as a stream-dependent property. The EOL convention of a stream (CR, CRLF, or LF) determines what sequence of characters on a file will be read (by READC, READ, etc) as the single internal end-of-line character CR. The EOL convention for a stream is defaulted to the usual value for the particular host or device (e.g. CR for IFS files, CRLF for TOPS-20 leaf files). It can be set explicitly by including for example (EOL CRLF) in the parameters argument to OPENFILE or OPENSTREAM, or by using the EOL attribute to SETFILEINFO. The EOL convention for an open stream can be obtained via GETFILEINFO.

#### <7> System level support for load-time constants.

System level support for load-time constants as provided in Interlisp-10 by the LOADTIMECONSTANTS Lispusers package. A side-effect of this is that ↑Y is now a readmacro in the CODERDTBL. This means that files compiled under Fugue.4, or earlier versions of Interlisp-D that contain ↑Y as a literal in a function definition will not load correctly into Fugue.6; new Fugue.6 .DCOMs must be made for these files. (Fugue.6 DCOMs can be back loaded into earlier Fugue sysouts except where there is a LOADTIMECONSTANT construct.)

#### <8> New/Improved LispLibrary and LispUsers packages:

N.B. Some current Library and Lispusers packages take advantage of new functionality not available before the Fugue.6 release. Thus not all new packages are compatible with pre-Fugue.6 sysouts. Tedit is one such package.

Complete documentation for these packages is contained in the Fugue.6 Release Kit.

- ATTACHEDWINDOW is a new package for "attaching" one window to another. Any number of windows can be attached to a window. ATTACHEDWINDOW supercedes MENUEDWINDOW which becomes a simple case of attaching a menu window to another window.

ATTACHEDWINDOW makes it easy to manipulate a group of window as a unit. Standard operations like MOVE, RESHAPE, OPEN and CLOSE can be done so that it appears to the user as if the windows are a single entity. Each collection of attached windows has one main window and any number of other windows that are "attached" to it. Moving or reshaping the main window causes all of the attached windows to be moved or reshaped as well. Moving or reshaping an attached window does not affect the main window. The initial motivation for attached windows was to allow multiple menus to be associated with the same window but there is no restriction on what windows can be attached.

- GRAPHER has several new, minor features. This release is almost compatible with your current code, although the graphs will look slightly different, so you need only revise if you want to take advantage of the new features.
  - General layout function: LAYOUTGRAPH is a combination of LAYOUTFOREST and LAYOUTLATTICE (which have been de-documented to discourage their use). It provides three kinds of format (tree, compact tree, and lattice) in four directions (left-to-right, right-to-left, top-to-bottom, and bottom-to-top). -- Icons as node labels: LAYOUTGRAPH and SHOWGRAPH both accept a NODELABEL which is a bitmap of arbitrary size.
  - Cyclic graphs are allowed in the lattice format. They generate boxed nodes instead of errors.
  - Documentation has been completely revised.
  - Defaults for fonts come from DEFAULTFONT in the current FONTPROFILE.
- FXPRINTER is a Library package which drives an Epson FX-80 printer using a serial (RS232) interface. This package has explicit functions to print files, text, bitmaps, and windows. On an 1108, the RS232 connection is made through the 1108's "Printer DTB" port.

- The following Lisp packages are new or changed since the Fugue.4 release:

BROWSER

ICONW

GRAPHZOOM

MENUEDWINDOW

NOTEPAD

RS232, RS232CHAT, RS232EXEC, RS232FTP, RS232LOGIN

SYSEEDIT

TEDIT, TEDITHCPY, TEDITMENU, TEXTOFD, TFBRAVO, IMAGEOBJ

#### <9> Memory management handles large reference counts.

Reference counts exceeding 63 are now properly handled via a reference count overflow table. This allows objects to be properly collected when the reference count again reaches zero.

#### <10> Sysouts may be installed directly from the 1108's rigid disk.

The Lisp Install Tool now allows the user to install a fresh sysout from one logical volume into another. This can be substantially faster than installing a sysout from a fileserver or floppy disks. See the *Xerox 1108 Users Guide* for details.

#### <11> Miscellaneous

- STORAGE function takes two optional arguments

The function STORAGE in Interlisp-D now takes two optional arguments for filtering the amount of information presented:

(STORAGE TYPES PAGETHRESHOLD)

If TYPES is given, STORAGE only lists statistics for those types. TYPES is an atom or list of types (either names or numbers). If PAGETHRESHOLD is given, then STORAGE only lists statistics for types that have at least PAGETHRESHOLD pages allocated to them. Note: this is completely incompatible with Interlisp-10's STORAGE.

- EDITPREFIXCHAR now defaults to NIL

TTYIN users: the variable EDITPREFIXCHAR is now by default NIL, meaning you can't type meta commands (this to avoid confusing users who don't know about it). If you want to be able to issue editing commands to TTYIN during your typein, you should either call (TTYINMETA T) to enable bottom-blank (STOP on 1108's) as a true meta key, or set EDITPREFIXCHAR to the character code of your preferred meta prefix (it used to be 193, for top-blank).

- GENSYM generalized.

GENSYM's first argument now can be a multicharacter atom or string and will be the prefix of the generated atom. Previously you could specify only a one-character prefix. Also, GENNUM is now initialized to 0 instead of 10000. This change substantially increases the number of generated symbols available to a program. By resetting the prefix, two or more sequences of generated symbols can be maintained.

- ATOMHASH # PROBES (new function)

(ATOMHASH # PROBES string) returns the number of probes it takes to find an atom in Interlisp's atom has table with PNAME = string, or NIL if no such atom is found.

- Missing characters restored for NS printers

Certain Interpress character code assignments prohibited some special characters from being printed on NS printers. (Most notably affected were Dollar, Leftarrow, Uparrow, and Hyphen.) The problem is fixed by remapping these codes within Lisp.

- Gacha replaced by Terminal for Interpress

The default FONTPROFILE now references the Terminal family of fonts instead of Gacha. Currently only fonts Terminal 8 and Terminal 12 are supported. Sites with NS printers should be sure Terminal has been installed.

#### KNOWN PROBLEMS WITH THIS RELEASE:

- Only the Installation Utility floppy can be used to partition the local disk in a rather stylized way. There is currently no Lisp utility which allows the user to declare the name and size for each logical volume.
- A sysout generated on an 1108 cannot be installed on an 1100.

- If you LOGOUT while some other process is actively writing a file, it is not guaranteed that anything reasonable happens to the file. The process system allows processes to prevent LOGOUT before completion (by using a BEFOREEXIT DON'T process property), but not all system facilities have been modified to use this mechanism.
- The caret is still global, rather than being a part of the window structure. This means that there are times where a caret gets left up in a window when it should have come down.
- The swapping file on the 1100 and 1132 (Lisp.VirtualMem) must be a small number (optimally 1) of disk segments, or swapping performance will degrade drastically. To create a (nearly) contiguous swapping file, use the Alto Exec command CREATEFILE.RUN on a newly-installed disk. The maximum size is 16,000 pages; this will guarantee that Lisp.VirtualMem will not become fragmented.
- Most system packages were written before multi-processing was added to Interlisp-D; some of these packages rely to some extent on there being only one process running, and access and alter global state accordingly. We have corrected many of these conflicts but have not yet completed this task. Avoid running more than one instance (from different processes) of DEdit, EMPRESS (hardcopy), MAKEFILE, the compiler, or Masterscope.
- The type attribute of floppy files is not fully supported. When a floppy file of type Binary is copied, it is assigned type Text. The work around is to set the global variable DEFAULTFILETYPE to BINARY and then copy the file (with COPYFILE). DEFAULTFILETYPE should be reset to NIL when the copy operation is finished.

## LOCATION OF FILES:

The following files are all available on [Maxc]<XSIS>:

[Site liaisons should move these files to their local file servers.]

- Lisp memory images files:  
Lisp.SYSOUT standard release virtual memory image
- Initialization for 1100 (Dolphin) and 1132 (Dorado):  
Lisp.run
- Microcode for 1100 (Dolphin) [new]:  
DolphinLispMC.eb for 3MB Ethernet  
XMBDolphinLispMC.eb for 10 MB Ethernet  
X3DolphinLispMC.eb both 3 and 10MB Ethernet, but no floating point
- Microcode for 1132 (Dorado) [new]:  
DoradoLispMC.eb
- Initial microcode for 1108 (Dandelion)  
LispSax000Initial.db

# Fugue.6 Release Documentation

## Addenda

May 1984

### Fugue.6 Sysout

The date of the Customer Version of the Fugue.6 Lisp.sysout is April 9, 1984. This date is displayed in the Logo window and in the typescript window when Lisp is initialized. This version supersedes all other Fugue.6 sysouts, regardless of creation date.

### New Machine Diagnostics Floppy

The "EI-Fixed Disk Diagnostic" floppy, Code 3Q83, has been replaced by a newer version and renamed "Fixed Disk Diagnostic", Code 1Q84. The two disks are functionally equivalent, and any reference in the documentation to the former also applies to the latter.

### Installing Fugue.6

- Xerox 1108 machine diagnostics should be run before installing Fugue.6. This procedure will help insure the hardware is in working order and that critical information on the rigid disk is correct. Diagnostics are run by 5-booting the "Fixed Disk Diagnostic" floppy. See Section 6 of the Xerox 1108 Users Guide.
- Before installing sysouts for the first time, use the Erase! command in the Install Lisp Tool to erase each Lisp volume. Thereafter, the Erase! command need not be used.

### Floppy Support

- Before writing a sysout to unformatted floppies, or to floppies which were formatted under Fugue.4, do (FLOPPY.FORMAT NIL NIL T) to ensure the formatting is complete and correct.
- Floppies written under Fugue.4 can usually be read under Fugue.6. However, Fugue.6 should not be used to write floppies created under Fugue.4. To reuse such a floppy, reformat it under Fugue.6 with FLOPPY.FORMAT.
- Unload floppies from the floppy drive when not in use. Unnecessary wear may result when floppy disks are left unattended for long periods in the drive unit.

### Loading Files from the Lisp Packages floppy

The Lisp Packages floppy contains complete file sets; i.e., all of the files on which any one file depends are also stored on the Lisp Packages floppy, whether they are updated in this release or not. This suggests that {FLOPPY} be added to the global variables LISPUSERSDIRECTORIES, DIRECTORIES, and FONTDIRECTORIES. Thus, the call (LOAD 'BROWSER.DCOM) will automatically load GRAPHER.DCOM and all of its dependencies, and all of the fonts on which the Grapher package depends.

## **New Tedit Interface**

An experimental, as yet undocumented, menu-driven interface to Tedit is available by loading TEDITMENU.DCOM and ATTACHEDWINDOW.DCOM from the Lisp Packages floppy. This menu is available by selecting the Expanded Window item in the standard Tedit menu.

---

---

**FUGUE.4 RELEASE NOTES**

---

---

This section describes the Fugue.4 release of Interlisp-D. Fugue.4 is the Customer Version of Fugue.3, which is a significant enrichment of its predecessors, Fugue.2 and Fugue.0.

THE FOLLOWING ITEMS ARE NEW OR REVISED IN FUGUE.3 RELEASE:

<3.1> Release Files for 1108, 1100, and 1132

- A distinction is made between supported Lisp Library files and unsupported Lisp User files.
- New documentation for Lisp system packages.

<3.2> Window/Display System Changes

- DISPLAYSTREAM datatype eliminated (merged with STREAM). Many programs which manipulate DISPLAYSTREAMs must be recompiled, a few may need to be edited.
- Various improvements to the Window system.

<3.3> 1108 -- Specific Improvements

- Improvements to reliability and performance
- Additional floppy support: can format, read, write

<3.4> New Interface For Printing

- PRINTERMODE is gone
- FONTPROFILE now has separate Interpress entry

<3.5> Improvements to Network Protocol Implementations

- NS protocols: a number of bugs fixed, still some performance problems
- File operations to PUP FTP-only hosts now supported
- Echo server, user tracing for Ethernet testing

- <3.6> Miscellaneous New Functions: APROPOS, PLAYTUNE, MACHINETYPE, SETPASSWORD
- <3.7> Known Problems With This Release

THE FOLLOWING ITEMS WERE ALSO PART OF THE FUGUE.2 RELEASE:

- <2.1> Multi-process Architecture Extended
- <2.2> TeleRaid: A Remote Debugging Aid
- <2.3> Timeouts For SAVEVM, RECLAIM In Background Now Notice Mouse Action.
- <2.4> EDITEMBEDTOKEN Is Now "&"; Affects Both DEDIT and EDITF. (formerly <esc> Or \*)
- <2.5> PROMPT # FLG Now Initialized to T: History Event Numbers Are Printed.
- <2.6> Miscellaneous New System Variables and Functions.

THE FOLLOWING ITEMS WERE ALSO PART OF THE FUGUE.0 RELEASE:

- <0.1> Fugue Runs Compatibly On All Three Machines of the 1100 Family
- <0.2> Window System Changes and Additions
- <0.3> DEDIT, TTYIN In Standard Loadup
- <0.4> All Alto Disk Partitions of 1100s and 1132s Accessible
- <0.5> New Implementation of Leaf
- <0.6> Incompatible Changes In Low-level Ethernet Code
- <0.7> DURATION, PROMPTFORWORD Packages Now In Standard Loadup
- <0.8> Additional Logical Arithmetic Functions (Inspired By CommonLisp)
- <0.9> Access to System Window And Background Menus

FUGUE RELEASE Notes

- <3.1> Release Files

A DISTINCTION IS MADE BETWEEN SUPPORTED LISP LIBRARY FILES AND UNSUPPORTED LISP USER FILES.

Formerly "LispUsers" software meant not only packages submitted by users, but also some packages which were maintained by Xerox. In order to promote the ongoing contribution of LispUsers software and to regularize the release cycle, we now distinguish between LispUsers and LispLibrary packages, the latter fully supported by Xerox.

NEW (NOT PREVIOUSLY ANNOUNCED):

ABC, EXPORTS.ALL (access to internal system data structures)

CMLSPECIALFORMS (from Common Lisp: CATCH and THROW, LET and LET\*, LIST\*, and DEFUN)

FTPSERVER (single-user Lisp PUPFTP server)

GATEWAY (forward packets between 10MB and 3MB ethernet)

GRAPHER (lay out graph structure on the screen)

GRAPHZOOM, SMALLFONTS, TIMESROMAND30.STRIKE,

TIMEROMAND72.STRIKE (zoom capability for GRAPHER package)

LISPLIBRARY.TTY (mini index/documentation.)

MAKEDIR (construct the pup-network naming database for use by GATEWAY)

PUPIDSERVER (tell 10MB Ethernet hosts their PUP number)

RDSYS, READSYS, REMOTEVMEM, VMEM (support for "TeleRaid" remote debugging)

NEW VERSIONS OF FILES FROM <LISPUSERS>

BIG (change font sizes for demos)

CMLARRAY (Common Lisp array facility: multi-dimensional, "Open-coding" etc.)

CIRCLPRINT (circular structure display)

COLOR, LLCOLOR, HLCOLOR, COLORDEMO, COLORPOLYGONS (support for color)

COLORPOLYGONS (color demo)

EVALSERVER (EVAL on other machines across net)

FILEBROWSER (file display, like Neptune)

ICONW (transparent icon windows)

LOGOCLOCK (clock in the Interlisp-D logo window)

PRINTER (support for a low-cost dot-matrix printer)

MENUEDWINDOW (attach menu's to windows)

POLYGONS (graphics demo)

READAIS (read .AIS sampled graphic images files, transform, halftone)

RS232, RS232CHAT, RS232FTP, RS232EXEC, RS232LOGIN (for RS232 serial port: drivers, dial-out "chat", MODEM protocol FTP, dial-in exec)

SINGLEFILEINDEX (indexed listing with table of contents)

TEDIT, TEDITFIND, TEDITHCPY, TEXTOFD (Interlisp-D Text Editor)

FILES MOVED DIRECTLY FROM <LISPUSERS> (UNCHANGED SINCE FUGUE.2):

BITMAPFNS (bitmap utilities)

CHECKSET (make sure files are compiled)

CLISPENG (program in English)

COMPILEBANG (compile without asking questions)

COMPILEFORMSLIST (compile variable-form into single function)

COMPMODEREC (implementation-dependent record declarations)

COREHAX (who's swapped in)

DATABASEFNS (Masterscope aid)

DECL (type declarations)

GCHAX (looking at the GC tables)

HANOI (graphics demo)

LAMBDATRAN (new kinds of functions)

LOGOCLOCK (analog clock in Interlisp-D logo window)

LOADDM (load Alto-style .DM files)

PEANO (graphics demo)

PQUOTE (print QUOTE as ')

READNUMBER (menu-based number pad)

SAMEDIR (MAKEFILE checks that output is on same directory as old version)

WINK (Marilyn Monroe winking)

THE FOLLOWING PACKAGES REMAIN ON <LISPUSERS>.

New (since Fugue.2):

ANIMATE (Bobrow.PA: smooth dragging bitmap; big arrow & hand)

BLACKOUT (HThompson.PA: black screen with bouncing cursor like DMT)

DISPLAYSTATS (Levy.PA: stats package interface to Grapher, to show dynamic call graph)

EDITHIST (DDyer@ISIB: keep track of edit history for files)

EMACS (Roach.PA: very small subset of EMACS built on top of TEDIT)

EXECFNS (Shulman@Rutgers: logical names for search paths in file names)

FACEINVADER (Shulman@Rutgers: game - shoot bouncing face)

READACFONTFILE (Lim.PA: Read .AC font files into internal format)

New versions (edited or recompiled since Fugue.2)

ACTIVEREGIONS (Barstow@SDR: mouse-sensitive regions)

BLTDEMO (Denber.wbst: bouncing ring & box)

EDITBITMAP (AHenderson.PA: More bitmap manipulations a la Notepad)

EDITMACROS (JonL.PA: useful tty-editor macros)

HISTMENU (Bobrow.PA: access history list via menu)

INMENU (Stefik.PA: different pop-up menus)

MAKEGRAPH (AHenderson.PA: built on Grapher, build graphs interactively)

NQUEENS (Schoen@SDR: Graphics demo of N-Queens problem)

ODOMETER (Sybalsky.PA: sequence of small windows roll like auto mileage gauge)

PROMPTREMINDERS (JonL.PA: periodically remind of events)

SOLITAIRE (Sheil.PA: graphics demo)

STYLESHEET (Stansbury.PA: create block of menus with multiple selections)

TTY (Stefik.PA: simple set of interactive TTY I/O functions)

TTYIO (Reid Smith@SDR: simple TTY I/O functions)

Old (unchanged since Fugue.2)

CROCK (Roach.PA: analog clock face)

DRAWFILE (Masinter.PA: read in Alto-Draw format files)

GLISP, GEV, GEVDEMO (Novak@UTexas-20: object-oriented data-independent programming)

HEADLINE (AHenderson.PA: make a big title on screen)

MATHFNS (Roach.PA: math fns, e.g., trig, log, hyperbolic fns & complex arithmetic)

MOUSECONFIRM (Yonke.PA: ask for click of mouse)

MULTIMENU (Schoen@SDR: create menus associated with main window, according to context)

MULTIW (Lane@SUMEX-AIM: hierarchical windows, which move, close, etc. in groups)

NOTEPAD (AHenderson.PA, Burton.PA: Artwork editor, brushes, symmetry)

PAGEFULLCTRL (Stefik.PA: different scrolling mode)

PAGEHOLD (JonL.PA: another variation on scrolling mode)

PATCHUP (Bobrow.PA: make patch file)

PERFORMTRAN (Kaplan.PA: new "Perform" keyword)

SAMPLER (Denber.wbst: graphics demo from Upstate New York)

SYSTAT (Roach.PA: window with monitor of system activity)

TMENU (Bobrow.PA: unread menus, windowshades)

TRACEIN (DonC@ISIF: single-step, trace, debug)

TRAJECTORY-FOLLOWER (AHenderson.PA: cause snake to crawl across a trajectory)

## DOCUMENTATION FILES

A major revision of the Interlisp Reference Manual will be available by the end of this month. Existing Interlisp-D sites will be receiving these manuals in the mail.

### <3.2> Window/Display System Changes

- DISPLAYSTREAM datatype eliminated (merged with STREAM)

In the move toward fully device-independent graphics, the DISPLAYSTREAM datatype has been eliminated; it is completely subsumed by the STREAM datatype. DSPCREATE returns a STREAM, and all the DSP--- functions work on this kind of object, without any coercion. DISPLAYSTREAMP is true for STREAMs returned by DSPCREATE. FONTCREATE has been changed so that it coerces the device attribute of a given font descriptor if possible instead of causing the "wrong font device" error. INTERPRESS is now a recognized font device, e.g., in DEFAULTFONT and FONTCREATE.

Many programs which manipulate DISPLAYSTREAMs must be recompiled or, in some cases, edited.

The new system is source-compatible with the previous system, with the exception of code that makes direct reference to the DISPLAYSTREAM record, either by field accesses or by (type? DISPLAYSTREAM --) constructions. Direct references to fields of the DISPLAYSTREAM record should be changed to use the functional interfaces; (type? DISPLAYSTREAM X) should be replaced with (DISPLAYSTREAM X). Other code does not have to be rewritten, but may have to be recompiled. Specifically, any function that calls (DSPxxx NIL ...) for xxx = XPOSITION, YPOSITION, XOFFSET, YOFFSET, LINEFEED, TEXTURE will have to be recompiled, because these forms compiled open as direct field accesses in the old system. The safest thing to do is to TCOMPL any file that manipulates the display. If the compilation succeeds, then the resulting .DCOM file is compatible with both old and new systems. If the compilation fails because the DISPLAYSTREAM record no longer exists, you must edit the file. Many LispUsers packages have been recompiled for this reason.

- VARIOUS IMPROVEMENTS TO THE WINDOW SYSTEM

The scroll handler now blocks so that system activity no longer stops when the cursor is in a scroll bar.

Moving windows from off the screen back onto the screen causes the newly exposed parts to be redisplayed.

PAINTW now brings up its menu in the background as well as in the window being painted. Thus if the painting window should be closed accidentally, it is still possible to quit PAINTW easily.

If a window is created without a title, a subsequently created title will be added on top of the window, not within it. In other words, the new windowheight will be the old windowheight plus the titlebarheight. Anything displayed in the window between its creation and its titling will not be obscured by the titlebar.

<3.3> 1108 (DANDELION) Specific Improvements

- IMPROVEMENTS TO RELIABILITY AND PERFORMANCE

A number of microcode and low-level system problems which have caused numerous crashes have been found and fixed in the recent past. Thanks to all of the initial users who took the time to report problems and let us TeleRaid them. While some problems still remain, the system is far more stable, and is faster thanks to new CONS and garbage-collection microcode.

- ADDITIONAL FLOPPY SUPPORT

Fugue.3 contains a preliminary version of support for the Dandelion floppy disk. You can now write to and read from the floppy disk drive on 1108s. The floppy drive device is called {FLOPPY}. There are 2276 pages available for the user's files on each floppy. For each file stored, there are two pages of storage overhead.

To format a floppy disk, insert it in the drive, and call (FLOPPY.FORMAT Name) where Name is a string or atom which will become the name of the disk. Formatting will erase the old contents of the disk. (Note that formatting the floppy uses enough cycles of the IO-Processor to make the system drop some keystrokes typed while formatting.)

To write to or read from a floppy disk, use FileBrowser, DIRECTORY, LOAD, OPENFILE, READ, PRINT, BIN, BOUT, GETFILEINFO, SETFILEINFO, GETFILEPTR, SETFILEPTR, etc. i.e., all standard I/O operations work.

There are still some problems with the floppy driver: e.g., incorrect error messages; no compaction of free blocks (so that creating and deleting files may result in a situation where the floppy device thinks there is no room even though very little space is in use); no monitor locks (avoid simultaneous access from separate processes!); and no interrupt protection (interrupting writing the floppy with a control-D may leave it in a state in which no new files can be written.) Use for backup, file storage and transfer seems to be reliable.

### <3.4> New Interface For Printing

- `PRINTERMODE` is gone: it is now inferred from the printer name.

The system now automatically selects the print format and transmission protocol for a printer; it is no longer necessary to set a global (`PRINTERMODE`). The variable `DEFAULTPRINTINGHOST` can be either a single printer name or a list of names. Names can either be the names of PUP-based press hosts or of NS-based Interpress hosts (e.g., `LISPPRINT:AAAI`, `PAPERMATE:PARC`).

The system uses the function (`PRINTERTYPE host`) to determine the type of a printer. If `host` is an atom, `PRINTERTYPE` first looks for a `PRINTERTYPE` property on `host`. If it doesn't find one, names with a colon in them (e.g., `LISPPRINT:`) are considered to be `INTERPRESS` printers, and otherwise, the type is assumed to be the value of `DEFAULTPRINTERTYPE`, initially `PRESS`. If `host` is a list, e.g. (`INTERPRESS GUTENBERG`), then `CAR` is taken as the `PRINTERTYPE`.

The functions `EMPRESS`, `PRINTERSTATUS`, `PRINTERPROPERTIES` are now all "Generic": they call the appropriate functions for formatting, transmission and interrogation according to the type of the printer.

When `DEFAULTPRINTINGHOST` is a list of printer names, the first "Appropriate" printer is used; for example, if you `EMPRESS` or `LISTFILES` an Interpress document, it will first look for a printer which can print Interpress documents, while a Press file will go directly to a press printer.

It is possible to add new printer types which key directly into `LISTFILES` and the `HARDCOPY` option in the background menu. For example, the `PRINTER` package on `<LispLibrary>` defines a new kind of printer type for printing on a local low-cost dot-matrix printer. Printer types are registered in the list `PRINTERTYPES`, which is a list of the form (`printertypes (property value) (property value) ...`). Each kind of printer (`Press = Dover/Penguin`, `Fullpress = Raven`, `Interpress = 8044/5700`) registers what kinds of files it can print directly, how to convert to a known format, how to scale bitmaps, create files from bitmaps, and print bitmaps. The variable `PRINTFILETYPES` documents the known kinds of files.

{LPT} DEVICE NOW RECOGNIZES PRINTER NAMES AS NAME FIELD

Now {LPT}FOO, where FOO is the name of a printer, will print on printer FOO when closed. For example,

```
(SETQ FILEHANDLE (OPENSTREAM '{LPT}QUAKE 'OUTPUT]
```

```
(PRINT "This will be printed." FILEHANDLE]
```

```
(CLOSEF FILEHANDLE]
```

will cause a file containing the sentence "This will be printed." to be printed on the printer QUAKE.

- FONTPROFILE NOW HAS SEPARATE INTERPRESS ENTRY

The fontprofile package now has, in addition to entries for default DISPLAY and PRESS fonts, a separate entry for INTERPRESS. The default FONTPROFILE for INTERPRESS has been modified to reference MODERN and CLASSIC fonts rather than TIMESROMAN and HELVETICA.

### <3.5> Improvements To Network Protocol Implementations

- NS PROTOCOLS

Fugue.3 contains a preliminary version of support for NS filing to Xerox 8030 file servers. The functions DIRECTORY, FILEBROWSER, INFILE, COPYFILE, LOAD, and MAKEFILE with NS file servers. Any device with a colon in its name is presumed to be accessible with NS protocols rather than PUP, (e.g., {StarFile:}. ) The general format of NS fileserver device names is {ServerName:Domain:Organization}; the device specification for an 8000-series product may contain the domain and organization; if not supplied directly, then they are obtained from the defaults, which themselves are found by a search for the nearest ClearingHouse. (Users may set CH.DEFAULT.DOMAIN and CH.DEFAULT.ORGANIZATION to be a default domain and organization instead. CH.NET.HINT is a hint to the clearinghouse-search path if your machine is not directly connected to a network with a clearinghouse.)

A number of bugs have been fixed in the implementation of NS Filing protocols since Fugue.2. We are still having intermittent performance

problems, however, which reduce the perceived bandwidth of an NS fileserver. File transfers often work, but sometimes connections time-out or bog down in the middle of transfer.

- FILE OPERATIONS TO FTP-ONLY PUP HOSTS NOW MORE FULLY SUPPORTED

The implementation of the PupFTP protocol (which supports transferring files sequentially only) has been improved. When sequential access to a file is appropriate, the use of PupFTP generally results in considerable speed improvement over Leaf, particularly for writing files on an IFS. Interlisp-D now tries to use PupFTP where possible for SYSOUT and for the destination file of a COPYFILE. Users can indicate that a file is going to be accessed only sequentially by including the attribute/value pair SEQUENTIAL T in the list of MACHINE.DEPENDENT.PARAMETERS passed to OPENFILE; then PupFtp will be used, if possible. The system now automatically shifts to the FTP protocol where Leaf is not available. If for some reason your file server supports PupFtp but you do not wish to use it, you can set the internal variable \FTPAVAILABLE to NIL. (Note that PupFtp has a much shorter timeout fuse than Leaf; thus files which are processed sequentially, but very slowly, should use the Leaf protocol if possible.)

FTP also supports an enumeration protocol; functions DIRECTORY, FILDIR, the FILEBROWSER Lisp Library package, now all work for any remote hosts which support enumerate in PupFtp.

- ECHO SERVER, USER, TRACING FOR ETHERNET TESTING:

The ethernet drivers have both NS and PUP echo-servers built into them, which will respond to the appropriate echo-me packets from other machines on the net. (E.g., it is possible to echo from a NS server to a Lisp workstation). In addition, Lisp has echo-users, documented in the new reference manual Ethernet chapters.

### <3.6> Miscellaneous New Functions

(APROPOS <pattern> <allflg> <quiteflg>) Scans all symbols in the system for one which has <pattern> as a substring, and prints out a line for each relevant item of that atom; relevant items are function definitions, global bindings, and non-null property lists. If <allflg> is NIL, then atoms without any relevant items are omitted

and also "internal" atoms are omitted ("Internal" currently means "pname begins with a \" or "result of GENSYM"). If <quietflg> is non-null, then no printing occurs, but a list of all selected atoms is returned.

(PLAYTUNE <Frequency/Duration.pairlist) will map down its argument, expecting each entry to be a dotted pair of frequency and duration and will beep the 1108 keyboard buzzer at that frequency for that amount of time. A NIL for the frequency means to turn the beeper off for that amount of time. Makes no sound on an 1100 or 1132. Note that the default "simulate" entry for control-G (ASCII BEL) on the 1108 will use PLAYTUNE to cause a short beep.

(MACHINETYPE) -- returns DORADO (for 1132), DOLPHIN (for 1100), or DANDELION (for 1108).

(SETPASSWORD host user password directory) -- sets values in the internal password database as if typed in via LOGIN.

### <3.7> Known Problems With This Release

- If you LOGOUT while some other process is actively writing a file, it is not guaranteed that anything reasonable happens to the file. The process system allows processes to prevent LOGOUT before completion (by using a BEFOREEXIT DON'T process property), but not all system facilities have been modified to use this mechanism.
- The {DSK} device on 1108s is only "ephemeral" and files placed there will not survive a re-loading or re-booting.
- The caret is still global, rather than being a part of the window structure. This means that there are times where a caret gets left up in a window when it should have come down.
- Formatting a new floppy with FLOPPY.FORMAT sometimes completes by falling into a break. Simple restart FLOPPY.FORMAT from the beginning (with REVERT followed by OK) and the formatting should complete ok.
- RS232 support for 1108's currently uses the so-called TTYPort, whose connector is generally labelled "Printer DTB" on the back of the 1108. In forthcoming releases, the true RS232 port will be used, and the TTYPort will be used only to drive a local Dot-Matrix printer. The following restrictions apply to Fugue.4.

1. While "Streaming" operations (e.g., writing to a printer) can operate as fast as 9600 Baud, operations such as Chatting and File Transfer are limited to 300 Baud.
  2. The DTR signal cannot be controlled from the 1108 -- it's always on. This will be fixed in a subsequent release.
  3. The 1108 has a female connector; it's internal wiring is like a DCE rather than a DTE; thus one has to wire up a "Null modem" with male connectors on each end. Pins 1 and 7 go straight through; pins 2 & 3 cross over; pins 6 and 20 cross over; pin 8 is jumpered to pin 4.
- Loading Lisp Library and Lisp User packages from floppy discs on the 1108 may fail when, for instance, (Load 'FOO.DCOM) attempts to autoload BAR.DCOM, and the two are on different floppies. Even pre-loading BAR.DCOM will not completely solve the problem in Fugue.4. (though it will be fixed a subsequent release). The current workaround is to explicitly load FOO.DCOM and BAR.DCOM, and return from any intervening FILE NOT FOUND breaks by typing (RETFROM 'FILESLOAD).

Users may find that a tty window (much like a break window) pops up unexpectedly for a process that apparently had no need for it. We have removed most such cases from system code; however, there are several cases in which user code can cause this behavior, where in earlier releases the code went unnoticed. A typical such case is where user code calls one of the DSPxxx operations, defaulting the displaystream. Unless the code REALLY wants to access the primary output of the process, the code should explicitly specify a destination.

The swapping file (Lisp.VirtualMem on 1100s and 1132s) must still be a "Small" number of disk segments. Swapping performance will degrade drastically when this number of segments is exceeded, and RAID will inform you of such happening. Generally, the setup of a disk partition with a swapping file of about 10000 pages is adequate for most users, but some have needed to go to 12000; "Setup" by CREATEFILE.RUN on a newly-installed disk will keep the number of segments as small as possible (often just one or two), and a few extensions beyond that will probably not cause any harm.

Most system packages were written before multi-processing was added to Interlisp-D; some of these packages rely to some extent on there being only one process running, and access and alter global state accordingly. We have corrected many of these conflicts but have not yet completed this task. Avoid running more than one instance (from different processes) of DEdit, EMPRESS (hardcopy), MAKEFILE, the compiler, or Masterscope.

#### THE FOLLOWING CHANGES WERE ANNOUNCED WITH THE FUGUE.2 RELEASE

##### <2.1> Multi-process Architecture Extended

Affects "Primary" I/O, (TTYDISPLAYSTREAM).

Window "Switching" between processes; new HELP interrupt.

It is important for ALL USERS to read the documentation relating to chapter 18 of the Interlisp Reference Manual.

Although the multi-processing environment is largely upward compatible with Chorus, there are some important differences in the behavior of mouse functions and menus.

#### GLOBAL INPUT/OUTPUT STATE IS NOW PER-PROCESS

There are several entities in the Lisp system that are "global" in Interlisp-10, and used to be global in Interlisp-D. These now have separate bindings in each process: primary input and output, terminal input and output, primary read table and terminal table, and the dribble file. This change is largely transparent to user code; however, any code containing the form (TTYDISPLAYSTREAM) MUST be recompiled, as this form had a macro that explicitly accessed a variable that is no longer global.

The default initial values for primary and terminal i/o when a process is created are "place holders". When the process actually tries to print/read to the primary input/output or the T stream without having installed some real stream as primary (using INPUT, OUTPUT or TTYDISPLAYSTREAM), a TTY window is created for the process. The user-settable variable DEFAULTTTYREGION is the region where these default windows come up. The function (HASTTYWINDOWP process) is true if the process has a tty window other than the initial "place holder"; (HASTTYWINDOWP NIL) refers to the current process.

Break windows are positioned near the TTY window of the broken process, as determined by the variable BREAKREGIONSPEC. This variable is a region whose LEFT and BOTTOM are an offset from the LEFT and BOTTOM of the TTY window where the break window should go; its WIDTH and HEIGHT determine the size of the break window.

#### KEYBOARD INPUT & TTY SWITCHING.

The model for specifying which process gets keyboard input is that "to type to a process, you click in its window." Any process desiring keyboard input should put its process handle as the PROCESS property of its window(s) [using WINDOWPROP]. The function TTYDISPLAYSTREAM does this automatically when the ttydisplaystream is switched to a new window. The window manager notices when you click in a window that has a PROCESS property, and makes that process be the TtyProcess, which causes all keystrokes to go to that process. Whenever the TtyProcess is switched, typeahead is saved, so that the input goes to the process that it was (presumably) intended for.

This default mechanism can be overridden. Writers of code that need more careful control over when and how the TtyProcess is switched, in particular those who called PROCESS.SWITCH.TO.WINDOW or used the PROCESS.IDLEFN, PROCESS.ENTRYFN and PROCESS.EXITFN properties in the old Process implementation, should read the relevant portion of the Process documentation for details of the new mechanism.

Programs that used to switch to PROMPTWINDOW to read are now discouraged from doing so, to avoid contention for that window. The function PROCESS.READ still exists, but you may not need it anymore. A process can simply READ, and the reading will happen in the process's own tty window, popped up if need be. An attempt to read underneath the mouse automatically grabs the tty process.

(READP T) now returns NIL immediately if the caller is not the TtyProcess (and there is no saved input). Implication: programs that called READP (or its internal subfunction \SYSBUFP) and then flashed a caret or took other action to indicate their being alive and/or receptive to input should consider testing (TTY.PROCESSP) first. The function (WAIT.FOR.TTY) efficiently blocks until (TTY.PROCESSP) is true.

## INTERRUPT CHARACTERS

Some interrupts, including BREAK (↑B), are still fielded by the TtyProcess. However, ERROR (↑E) and RESET (↑D) are preferentially taken by the mouse process if it is not "idle" (otherwise by the tty process, as before). The HELP interrupt (↑H, though many users move it to ↑G) puts up a menu of processes asking which one the user desires to interrupt, and then performs the interrupt in that process.

## MISCELLANEOUS

The mouse now runs in its own process, called MOUSE, separate from the other background tasks, such as writing dirty pages back to the disk.

The default value of the RESTARTABLE argument for ADD.PROCESS is now to never restart. If you want a process to restart when a HARDRESET occurs (the Fugue.0 default), specify a RESTARTABLE of HARDRESET.

Scroll holding works for the tty window of each process. Of course, if you use the normal mechanism, and the hold happens in other than the tty process, you have to click in the held window before you get to type something to release the hold.

There is a new item in the system background menu labeled PSW, which brings up a process status window.

### <2.2> TeleRaid: A Remote Debugging Aid

The 1108 has no Raid debugger (since Raid is written in BCPL), but does provide a low-level "TeleRaid" service when it would otherwise fall into RAID. When the machine is in TeleRaid, it can be debugged from another machine, or in some cases the user can issue commands to continue or break into the computation in limited ways. 1100s and 1132s can also run TeleRaid.

Once a machine is in TeleRaid, then another may be used to debug it by calling (TELERAID <host>), where <host> is the Pup name or number of the machine running the TeleRaid server. The function TELERAID is not in the standard loadup; to load it, you must load the files READSYS.DCOM, RDSYS.DCOM, VMEM.DCOM, and REMOTEVMEM.DCOM. The user interface for TELERAID is similar to that of Raid; type ? for an enumeration of commands.

When the maintenance panel of an 1108 indicates a Lisp-induced halt, pressing the UNDO key starts the TeleRaid server. TeleRaid changes the cursor to the TeleRaid cursor, takes over the ethernet controller and keyboard, then waits for commands from either the Ether or the keyboard. Keyboard commands are given by holding down the control key (or PROPS on the standard Dandelion keyboard) and striking another key. As you strike a key, the cursor changes to give feedback about the command you are about to execute; the command is executed when you let go of the key, but if you let go of the command key first, the command is aborted. The commands are as follows:

↑N - like Raid ↑N: continue the computation.

↑D - like Raid ↑D: do a HARDRESET.

↑B - cause a break underneath the error.

↑P - display the machine's Pup host number (decimal) in the maintenance panel

(for remote debugging).

TeleRaid refuses to execute the "↑B" command if the user is executing in a place (e.g., inside of a garbage collection) that would be dangerous to allow a user break.

You can put an 1100 or 1132 (Dolphin or Dorado) into TeleRaid server mode by giving the "R" command to Raid and thus remotely debug it or make use of TeleRaid's ↑B command (nothing corresponding to this command is available in standard RAID).

### <2.3> Timeouts For SAVEVM, RECLAIM In Background Now Notice Mouse Action

The background RECLAIM and SAVEVM are no longer handled by PERIODICALLYRECLAIM on PROMPTCHARFORMS, but run in the background process, and now pay attention to mouse actions as well as typein. A background RECLAIM happens if the user has made no keyboard or mouse action for RECLAIMWAIT seconds. A background SAVEVM happens, if the virtual memory conditions are right, if the user is in tty input wait and has made no keyboard or mouse action for SAVEVMWAIT seconds (note: this is a change in the meaning of SAVEVMWAIT).

- <2.4> EDITEMBEDTOKEN Is Now "&", Affects Both DEDIT And EDITF. (Formerly <esc> Or \*)

The variable EDITEMBEDTOKEN holds the token used in the embedding commands of both the display and tty-based editors. Its initial value is &, which is a change for BOTH editors (formerly, it was <esc> for DEDIT, and \* for the Teletype-style). Users are, of course, free to change the value in their init files.

- <2.5> PROMPT # FLG Now Initialized To T: History Event Numbers Are Printed

The variable PROMPT # FLG now initialized to T, so that history event numbers are printed out at the executive, making it easier to use history commands. Formerly, PROMPT # FLG was initialized to NIL.

- <2.6> Miscellaneous New System Variables And Function

MIN.SMALLP, MAX.SMALLP, MIN.FIXP and MAX.FIXP: [Variables]

These are respectively the min and max on the range of the functions SMALLP and FIXP.

NETWORKOSTYPES [Variable]

For proper service from file servers other than the Xerox IFS or Xerox NS, you should add entries to the system a-list NETWORKOSTYPES associating the host name (all uppercase) with its operating system type, currently one of TENEX, TOPS20, UNIX, VMS. E.g., (ADDTOVAR NETWORKOSTYPES (MAXC2 . TENEX)).

(RESTART.ETHER) [Function]

Under rare conditions, the Dandelion Ethernet driver can get into a bad state where the Ethernet appears totally unresponsive. Calling RESTART.ETHER will try to reinitialize all the appropriate items to get you going again.

THE FOLLOWING ITEMS WERE ALSO PART OF THE FUGUE.0 RELEASE

- <0.1> Fugue Runs Compatibly On All Three Machines Of The 1100 Family: The 1100 (Dolphin), The 1108 (Dandelion) And The 1132 (Dorado)

Fugue Interlisp-D will run on the 1108 (Dandelion processor) as well as the 1100 (Dolphin) and 1132 (Dorado). 1108 configurations supported include the 8011 (10MB SA1000 disk), 8012 (29MB SA4000 disk), 8014 (40MB Quantum disk) with memory sizes from 1 MByte to 1.5 MByte. All versions are completely

compatible -- it is possible to take ANY Interlisp-D memory image and move it directly from one machine to another. The 1108 Interlisp-D is implemented solely in microcode and Lisp; it has no Mesa or BCPL, and its microcode fits in the standard 4K control store. It can be installed from floppy disks or from a file server.

<0.2> Window System Changes And Additions:

The function CURRENTDISPLAYSTREAM, and the notion of a "primary" display stream have been removed from the system. Display functions now default their destination stream to the "primary output", just as other output functions do. If a DSPxxx function is called with displaystream NIL, and the primary output is NOT a stream of type display, an error is generated. Any user code that refers explicitly to CURRENTDISPLAYSTREAM must be changed; in addition, user code that calls displaystream operations defaulting the displaystream argument may need to be examined.

Calls to CURRENTDISPLAYSTREAM with the intent of determining the font of a prototypical display stream can use the newly provided function DEFAULTFONT, below.

NEW FUNCTIONS

(DEFAULTFONT DEVICE FONT NOERRORFLG) [Function]

Returns the font that is used as the default for the device DEVICE. If FONT is a font, it replaces the default for the device DEVICE.

The functions OPENWP and OPENWINDOWS are now synonyms of (and the preferred names for) ACTIVEWP and ACTIVEWINDOWS, respectively.

(CREATEREGION LEFT BOTTOM WIDTH HEIGHT) [Function]

Returns an instance of the REGION record, with LEFT, BOTTOM, WIDTH and HEIGHT components.

Functions BITMAPWIDTH, BITMAPHEIGHT, and BITSPERPIXEL were added to facilitate access to the fields of a bitmap. The function PRESSBITMAP is now in the standard loadup.

(FILLCIRCLE X Y RADIUS TEXTURE DISPLAYSTREAM)

[Function]

Fills a circular area of radius RADIUS about the point (X, Y), in the window or displaystream DISPLAYSTREAM with the texture TEXTURE.

<0.3> DEDIT, TTYIN in standard loadup

DEDIT:

DEDIT is installed as the "standard" editor. DEDIT documentation is in the Interlisp-D Users Guide and will be in the new Interlisp Reference Manual. The version in Fugue is a completely new re-implementation of the version of former releases, and should be quite apparently faster. The function EDITMODE now takes TELETYPE instead of STANDARD to describe the "TTY" editor.

NEW FEATURES

A Break command (does a BREAKIN AROUND the current expression). DP now allows a second argument which it will interpret as a property to be edited, i.e. DP(FOO MACRO). The single argument form gets the whole property list as before.

Shift selection (COPY) remains active even when DEdit is not. Thus one can unread expressions from DEdit windows into the typescript window. (Selections are otherwise disabled when they would be inappropriate, e.g. under nested computations).

(RESETDEDIT) completely reinitializes DEdit if it gets badly scrambled.

Switching to tty (or other) editors: Subcommands on Edit allow multiple options of using DEDIT, TTYIN, or the (old) teletype editor on either the current expression or on its definition.

One can now give TTY editor commands directly into the typein buffer by prefixing them with ↑Z. This gives full access to the programmable characteristics of the TTY editor -- you can define your own edit macros or use the more complex ones (SWAPC, IFY, BQUOTE). A read macro on ↑Z interprets the rest of the line as an EditCom which will be executed when the line is closed. Likewise, you may enjoy ↑S (Substitute old new) and ↑F (Find) commands. Commands are defined by editing the variable DEDITTYPEINCOMS in what should be a fairly obvious way, and then RESETDEDITing.

## TTYIN

TTYIN is installed as the standard "line buffer" -- the mini-editor for keyboard input from the so-called T stream. TTYIN features editing of the type-in buffer with mouse or control-key commands, and "automatic word completion".

## &lt;0.4&gt; All Disk Partitions Of 1100s And 1132s Are Now Accessible From Interlisp-D

The low level implementation of the disk drivers has been substantially revised, with a consequence that Interlisp-D can access partitions other than the one which was booted. If the other partition is password-protected, Lisp insists on the correct password before accessing any files. Partitions are denoted by {DSK1} for Partition 1, {DSK2} for Partition 2, etc. All file operations (including SYSOUT, the filebrowser, DIR command, etc.) work for other partitions. However, it is not currently possible to run a sysout stored on another partition.

## &lt;0.5&gt; New Implementation Of Leaf

Fugue contains a new implementation of the Leaf filing protocol, which tolerates simultaneous access to the same server from different processes and permits more overlapping of Lisp computation with file server operations, allowing for improved performance. A corollary of the latter that you should be aware of is that a file is not closed the instant that CLOSEF returns--Lisp is closing the file "in the background". It is therefore more important than ever that you exit Lisp "normally", via (LOGOUT), or (LOGOUT T), rather than boot the machine or exit via Raid.

## &lt;0.6&gt; Incompatible Changes In Low-level Ethernet Code

PUP record declarations, GETPUP, etc.

The ethernet code was substantially rewritten for Fugue to accommodate the 10MB and Network System protocols, and also to put into Lisp all the background code formerly written in BCPL. A number of incompatible changes resulted: the PUP record changed, necessitating at least the recompilation of all pup user code; GETPUP returns a brand new pup, rather than copying the incoming pup into a user-supplied pup datum; SENDPUP synchronizes differently with the transmitter; CREATESOCKET and FLUSH SOCKET were renamed OPENPUP SOCKET and CLOSEPUP SOCKET.

When a machine starts up, the Ethernet code gets the time from a server on the local net, if possible. The information supplied by the server includes the local time zone. Users who are not on an Ethernet and not in the Pacific timezone need to set the global variable `\TimeZoneComp` in the local disk's `INIT.LISP`. The value of `\TimeZoneComp` is the number of hours west of Greenwich (negative if east).

#### <0.7> DURATION, PROMPTFORWORD Now In Standard Loadup

From DURATION: the functions `SETUPTIMER` and `TIMEREXPIRED?` are to help write code that "times out"; there are several new I.S.OPRS to facilitate scoping such code. Complete documentation is in the new manual.

From PROMPTFORWORD: a new function `PROMPTFORWORD` has replaced the `LispUsers` package called `READAWORD`. It provides a system-level alternative to `ASKUSER`, with prompting similar to what the Alto Executive provided for login and password reading. Complete documentation is in the new manual, and for a short time will continue on `<Lisp>Fugue>Promptforward.press`.

#### <0.8> Additional Logical Arithmetic Functions (Inspired By CommonLisp)

`LOGNOT`, `BITTEST`, `BITCLEAR`, `MASK.1'S`, `MASK.0'S`,  
`LOADBYTE`, `LDB`, `DEPOSITBYTE`, `DPB`, `ROT`

The following "logical" arithmetic functions are derived from Common Lisp, and have both macro and function definitions (the macros are for speed in running of compiled code). They have the following interpretations:

<code>(LOGNOT x)</code>	<code>= = (LOGXOR x -1)</code>
<code>(BITTEST x mask)</code>	<code>= = (NOT (ZEROP (LOGAND x mask)))</code>
<code>(BITCLEAR x mask)</code>	<code>= = (LOGAND x (LOGNOT mask))</code>
<code>(BITSET x mask)</code>	<code>= = (LOGOR x mask)</code>
<code>(MASK.1'S pos size)</code>	<code>= = (LLSH (SUB1 (EXPT 2 size) pos)</code>
<code>(MASK.0's pos size)</code>	<code>= = (LOGNOT (MASK.1'S pos size))</code>
<code>(LOADBYTE x pos size)</code>	<code>= = (LOGAND (LRSH x pos) (MASK.1'S 0 size))</code>

```
(DEPOSITBYTE x pos size byte)  = = (LOGOR (BITCLEAR x (MASK.1'S
                                     pos size))
                                     = = (LLSH (LOGAND byte (MASK.1'S 0
                                     size)) pos))
```

The notion of a "byte specifier" has been added; from a pair of position and size arguments, a byte-spec is constructed by the macro BYTE [note reversal of arguments as compared with above functions] (BYTE size pos). Similarly, the macros BYTESIZE and BYTEPOSITION will select out the two fields [currently, byte-specs are implemented as a typerecord; CommonLisp leaves unspecified whether there are range limitations on "size" or "pos"] Two more "byte" functions are provided, with compiler macro support also:

```
(LDB bspec val)                = = (LOADBYTE val (BYTEPOSITION bspec)
                                     (BYTESIZE bspec))

(DPB n bspec val)              = = (DEPOSITBYTE val (BYTEPOSITION bspec)
                                     (BYTESIZE bspec) n)
```

The final function in this series is not quite so easy to describe -- ROT for "Rotate bits in field".

(ROT x n fieldsize) is a slight extension of the CommonLisp ROT function. It performs a bitwise left-rotation of the integer x, by n places, within a field of fieldsize bits Wide; bits being shifted out of the position selected by:

(EXPT 2 (SUB1 fieldsize)) will flow into the "units" position. The optional argument fieldsize defaults to "cell" size (the integerlength of the current maximum fixp), and must either be a positive integer, or else be one of the literals CELL or WORD. In the latter two cases the appropriate numerical values are respectively substituted.

A macro optimizes the case where n is 1 and the fieldsize is 16 (or WORD).

<0.9> Access To System Window And Background Menus:

New functions DOWINDOWCOM, DOBACKGROUNDCOM

New vars: xxxMenu and xxxMenuCommands for xxx in {Window, Icon, Background}

There are six user-accessible variables for controlling the contents of the standard Window menu, Icon menu and Background menu. For each menu, there is a variable xxxMenu that caches the actual menu, and a variable xxxMenuCommands that holds the commands for the menu, in the format of an ITEMS field of a MENU. The menu is recreated from the list of commands whenever the xxxMenu menu variable is set to a non-MENU (e.g., to NIL). The variables are:

WindowMenu and WindowMenuCommands -- the menu (and its commands) that is brought up in response to a right button in a window. A command in WindowMenuCommands should return a function name that will be APPLYed to the window.

IconWindowMenu and IconWindowMenuCommands -- analogous, used in response to a right button in a shrunken window.

BackgroundMenu and BackgroundMenuCommands -- the menu (and its commands) that is brought up in response to a right button in the background. A command in BackgroundMenuCommands should return a form that will be EVALed.

For example, to add commands to the window menu, simply add the commands to WindowMenuCommands, and set WindowMenu to NIL. To change the font used in the menus, change MENUFONT and set all the xxxMenu variables to NIL.

The following functions provide a functional interface to the interactive window operations so that user programs can call them directly:

(DOWINDOWCOM WINDOW)

[Function]

If WINDOW is NIL, it calls DOBACKGROUNDCOM.

If WINDOW is a shrunken window, it brings up the IconWindowMenu.

If WINDOW is a unshrunken window, it brings up the WindowMenu.

The initial items in these menus are described above. If the user selects one of the items from the provided menu, that item is APPLIED to WINDOW.

(DOBACKGROUNDCOM)

[Function]

Brings up the BackgroundMenu. The initial items in this menu are described above. If the user selects one of the items from the menu, that item is EVAL'd.